

Exchange Server 2010 SSL Certificate Installation Procedure:

- 1. Download and open the file containing your certificate. Your certificate file will be named your_domain_name.cer.
- 2. Copy the your_domain_name.cer file to your Exchange server.
- 3. Start the Exchange Management Console by going to Start > Programs > Microsoft Exchange 2010 > Exchange Management Console.
- 4. Click the link to "Manage Databases", and then go to "Server configuration".
- 5. Select your certificate from the menu in the center of the screen (listed by its Friendly Name), and then click the link in the Actions menu to "Complete Pending Request".

Microsoft Exchange Microsoft Exchange On-Premises (v Microsoft Exchange On	📱 Server Configur	Actions			
	P Create Filter	Server Configuration			
	Name -	Role	Version	÷	Modify Configuration Domain Cont
	WIN-LWN7MEAN9KO	Hub Transport	Version 14.0 (Build 639.11)		Export List
					View
					G Refresh
					Help
	1				
					WIN-LVN7MEAN9KO
		👘 Manage Hub Transport Role			
	WIN-LVN7MEAN9	Manage Diagnostic Logging Prop.			
	Exchange Certificates	111	A		Enter Product Key
	Name +	SelfSigned	Status	Services	New Exchange Certificate
	Microsoft Exchange	True	The certificate is valid for	SMTP	Import Exchange Certificate
		1			Droperties
					DigiCert UC Certificate
					Se some reneration
				1	

6. Browse to your certificate file, then click Open > Complete.



7. Now, to enable your certificate for use, go back to the Exchange Management Console and click the link to "Assign Services to Certificate."

Manage Exchange	R. c. c. c.	Actions				
Contraction Configuration Configuration Configuration Configuration Configuration Configuration Server Configuration Reciptent Configuration Toobox	Server Configu	Factors Configuration				
	* Create Filter				Server Comparation	
	Name +	Role	Version	() () () () () () () () () ()	Modify Configuration Domain Con	ıtr
	WIN-LVN7MEAN9KO	Hub Transport	Version 14.0 (Build 639.11)	40	Export List	
				100	View	•
			-	1	@ Refresh	
					Help	
						4
					WIN-LVN7MEAN9K0	
	-	🛅 Manage Hub Transport Role				
	WIN-LVN7MEAN9	Hanage Diagnostic Logging Prop	a			
	Exchange Certificates	Enter Product Key				
	Name -	Self Signed	Status	Services	New Surbases Configure	
	DigiCert UC Certificate	t False	The certificate is valid for	None	Le) New Exchange Certificate	
	Microsoft Exchange	True	The certificate is valid for	SMTP	Import Exchange Certificate	
					Properties	
					DigiCert UC Certificate	
					Proof Exchange Certificate	
					Assion-Services to Certificate	
				-	Las Renew Exchange Certificate	
					> Remove	
					A 10.000 (0.000)	

- 8. Select your server from the list provided, then click Next.
- 9. Select the services for which you would like to enable your new certificate, click Next > Assign > Finish.

Your certificate should now be Installed and Enabled for use with Exchange.