

## Juniper Secure Access VPN SSL Certificate Installation Procedure:

- 1. Copy and paste the Server Certificate (including the BEGIN and END tags) into a text editor such as Notepad and save it on your Local Computer.
- In the admin console, choose System > Configuration > Certificates > Device Certificates.
- 3. Under Certificate Signing Requests, click the Pending CSR link that corresponds to the signed certificate from Entrust.

Junipe	r'		
Root 🛩 Go	Central Manager Root		
System     Setur     Configuration     Network     Clustering     Virtual Systems     If-MAP Federation     Log/Monitoring     Authentication     Signing In     Endesent Security     Auth.Servers     Advertisetshore	Configuration Ucensarg Security Certificates DM Device Certificates Trusted Client CAs Tru Specify the Device Certificate(s). If you custom Intermediate Device CAs. Import Certificate & Key Delet	E Agent NCP Sensors Client Types uted Server CAs Codectigning Certificates don't have a certificate yet, you can crea e	Secure Meeting Virtual Desktops Use
Admin Realms Admin Rofes Deers User Realms User Roles Resource Profiles Resource Policies Hainbenance	Certificate issued to	Issued by Entrust Certification Authority - LIE	Valid Dates Jun 10 19:13:38 2010 GMT to Jun 10 19:43:37 2011 GMT
System Import/Export Push Config Archiving Troubleshooting	New CSR Delete Certificate Signing Requests Pending CSR for juniper2.entrust.com		Created 6/22/2010 16:18:02



4. Under Import signed certificate, browse to the certificate file and then click Import.

og/monitoring			
Surthern Gicartion	People Cortificate Signing Peoplest		
igning In +	Pending Certificate Signing Request		
ndpoint Security =			
uth. Servers	CSK Details		
Moninistrators	Common Name: Juniper.entrust.com		
dmin Realms 🔹	Created: 6/10/2010 18:49:36		
dmin Roles 👘	Org. Name: Entruit Inc. Locality: Ottawa		
kers	Ung unit name: customer service state: Unitano Email Address: susnostifientust.com Countru:CA		
zer Realmz	Key Size: 2048 bits		
ser Roles			
esource Profiles	Back to Device Certificates		
esource Poncies +	KARL VE FALLER FOR THE SECTION OF A SECTION		
cans be same o	Step 1 Send CSP to Certificate Authority for signing		
ystem -	step 1. Send Cak to certificate automy for signing		
ush Config	of the following ways:		
chiving -			
oubleshooting -	<ul> <li>Save the text as a .cert file and attach it to an email message to the CA</li> </ul>		
	Paste the text into an email message to the CA		
	<ul> <li>Paste the text into a Web form provided by the CA</li> </ul>		
2000			
	Note: Manage the CSR process carefully. If you submit more than one CSR to a CA, you may be billed for each		
	MITCS/CC/AIC/CO/MANAGOVCA/LBANGKA PYTANNENDAUDAVDUOOTPudDhaDhemiumOBr		
	DOVDVOOHENZPOHENDAZEXGTAXBONVDATTANDARANGYTVOTATA		
	BAOTDEVudHJ1c3QgSW5jLjEcHBoGA1UEAxHTanVuaXB1c151bnRydXN0LmNvbTE1		
	BCAGCSqGSIb3DQEJARYTC3VecG9ydE8lbnRydXNOLmNvbTCCASIeDQYJKoZIhvcN		
Contraction of the			
	Step 2. Import signed certificate		
	When you receive the signed certificate file from the CA, select it below and click Import. This will add the sign		
C. C. S. S. T. C.	Signed certificate: C-Documents and Setting Browse		
	Innext		
	7 B		



5. You should see a message confirming that the certificate has been imported successfully. The Server Certificate should appear in the list of Device Certificates.

Muniper*				
Root Go				
System     Status     Configuration     Network     Clustering     Virtual Systems     IIF-MAP Federation     Log/Monitoring     Authentication     Signing In     Endpoint Security     Auth. Servers     Advantist a tors	Configuration Ucensing Security Certificates DM Device Centificate Trusted Client Cas Tru	Al Agent NCP Sensors Ceent Types usted Server CAs Codersigning Certificates don't have a certificate yet, you can crea 18	Secure Meeting Virtual Des	
Admin Realms Admin Roles - Users	Certificate issued to	Issued by	Valid Dates	
	D juniper.entrust.com	Entrust Certification Authority - L1E	Jun 10 19:13:38 2010 GMT 19:43:37 2011 GMT	
User Realms User Roles Resource Profiles Resource Policies – Individuation	Diuniper.entrust.com	Entrust Certification Authority - LIC	Jun 10 19:13:38 2010 GMT 19:43:37 2011 GMT	
System - Import/Export - Push Config - Archiving - Troubleshooting -	New CSR Delete	L§	-	
	Gertificate Signing Requests		Created	

## Steps To Import the Intermediate Certificate onto The SSL VPN Device:

- **1.** Log in to the admin console
- 2. Go to: System > Configuration > Certificates > Device Certificates



3. Click Intermediate Device CAs.

Status +	Configuration		
Configuration 🔷 🔸			
Network *	Licensing Security Certificates	DMI Agent NCP	Sensors Client Types
Clustering +	Loonsing Goodine, Continented	Dira rigone inor	
Virtual Systems 🔿	Device Certificates   Trusted Client CAs	Trusted Server CAs	Code-signing Certificates
IF-MAP Federation +			
Log/Monitoring +	Specify the <u>Device Certificate(s)</u> . If you don't have a certificate yet, you can cre- custom Intermediate Device CAs.		
- Authentication			
Signing In 📀 🔸			
Endpoint Security 🔸			
Auth. Servers	Import Certificate & Key	Delete	
- Administrators			
Admin Realms 🔸	Certificate issued to	Issued by	
Admin Roles 🔹 🔸	Eltest lolocal	test lolocal	
- Users		(0)(10)0001	
User Realms 🛛 🔸			
User Roles 🛛 🔸			
Resource Profiles 🔸			
Resource Policies 🔸			
- Maintenance			
System +			
Import/Export +			

4. Click Import CA Certificate and import the Intermediate certificate

- System	
Status	Configuration > Device Certificates >
Configuration (	Intermediate Device CAs
Network	
Clustering	The following intermediate certificate authorities are used with Device Certificates.
Virtual Systems	
IF-MAP Federation	Import CA Certificate Delete
Log/Monitoring	
<ul> <li>Authentication</li> </ul>	CA certificate
Signing In	
Endpoint Security	
Auth. Servers	🔲 🔲 🗔 Comodo Class 3 Security Services CA
- Administrators	
Admin Realms	
Admin Roles	
- Users	
User Realms	
User Roles	
Resource Profiles	
Resource Policies	
- Maintenance	
System	